

Splunk Universal Forwarders

By: Ryan Stewart

Installing Splunk Universal Forwarder for Windows


In this training session, I'll install the Splunk Universal Forwarder in its default configuration to facilitate the sending of Windows logs to Splunk.

- 1. Prepare for Installation:
 - Go to the Windows computer.
 - Download the Splunk Universal Forwarder setup file.

Splunk Universal Forwarder 9.0.0.1

Universal Forwarders provide reliable, secure data collection from remote sources and forward that data into Splunk software for indexing and consolidation. They can scale to tens of thousands of remote systems, collecting terabytes of data.

Choose Your Installation Package




2. MD5 Verification:

- Read the Splunk General Terms and download the MD5 checksum.
- Open the MD5 file and verify the checksum using PowerShell:


```powershell

Get-FileHash .\splunkforwarder-9.0.0.1-9e907cedecb1-x64-release.msi -Algorithm md5


- Confirm that the calculated MD5 matches the provided checksum.
- 3. Launch Setup:
  - Launch the setup file and read the License Agreement.
- 4. License Agreement:
  - Accept the License Agreement.




- Select "an on-premises Splunk Enterprise instance" for on-premise server installation.
- 5. Configuration:
  - Use the default configuration.
  - Provide a username for the Universal Forwarder.



- Specify the IP or Hostname and port (usually 9997) of the receiving indexer. Use the IP if there is no DNS in your lab.



- 6. Installation:
  - Launch the installation.
- 7. Check Universal Forwarder Installation:
  - Open services.msc and confirm that the "SplunkForwarder Service" is running.



- Use PowerShell to check if communication is open:

### powershell


Test-NetConnection -Computername Splunk IP -port 9997

```
PS C:\Users\nucl3arsnake> Test-NetConnection -Computername 192.168.10.1 -port 9997


ComputerName : 192.168.10.1
RemoteAddress : 192.168.10.1
RemotePort : 9997
InterfaceAlias : Ethernet
SourceAddress : 192.168.10.10
TcpTestSucceeded : True
```

\*Congratulations, Splunk Universal Forwarder for Windows has been successfully installed.\*

- 8. Verify on Splunk:
  - Go to your Splunk Server.
  - Navigate to Settings > Forwarder management.



- Confirm that your Windows computer is visible on this page.



- If the computer is not visible after a few minutes, restart the Splunk Universal Forwarder service and check the connection between the client and server.